

Minecraft Bedrock Server ProRedLine©






Table of contents

Installing your new server	2
The Emails You Will Receive and the Installation Process	2
The specific options for your server	2
Startup tab.....	2
Legal information for your server	3
Reinstall your server	4
Support for your server	4



Installing your new server

Great! You've just purchased a Minecraft Bedrock server subscription on ProRedLine. Once payment is completed, a new server will be installed on your account. The process is as follows:

The Emails You Will Receive and the Installation Process

First, you will receive an email from the webshop informing you of the current status of your order. If payment has been completed, the order will begin processing. After a few minutes, you will receive another email indicating that the order has been completed, meaning your server installation will start.

If you are a new customer, you will receive a third email notifying you that a new account has been created at <https://dashboard.proredline.com>. This email will include a password reset link to set up your first password. Make sure to remember this password. If you wish to set up MFA, please refer to the Server Dashboard Manual you received.

Once your server installation is complete, you will receive the final email notifying you that the server is ready for use. At this point, you can sign in to your account at <https://dashboard.proredline.com> and access your server dashboard.

For further information regarding the dashboard functionality, please refer to the **Server Dashboard Manual** you received.

The specific options for your server

Once the server has been installed, you will need to configure it before it can run as expected. This configuration process will vary depending on the type of server you've purchased. Please follow the specific instructions provided in the server manual to ensure your server is properly set up and optimized for your needs.


Startup tab

On your server's dashboard, go to the "Startup" tab. Here, you will find several settings that you can configure according to your specific needs. Below is a list of options available for your ARK: Survival Ascended server in the "Startup" tab:

1. STARTUP COMMAND and DOCKER IMAGE are read-only variables and cannot be modified.

Variables **Nukkit**:

1. **SERVER JAR FILE.** This is the name of the JAR file used to run the server. It is not recommended to change this value, but it is possible. Changing this may break your server.
2. **NUKKIT VERSION.** This indicates the version of Nukkit currently utilized on your server. By default, the latest version is used.



Variables **Pocketmine:**

1. **VERSION TO INSTALL.** Here, you can select the version to install, either the latest version of PM5 or the latest version of PM4.

Variables **Vanilla:**

1. **BEDROCK VERSION.** The default is the latest version, but you have the option to change the server version to any version of your choice.
2. **SERVER NAME.** This is the in-game name of your server. You can modify it to any name you prefer.
3. **GAMEMODE.** You can set this to Survival, Creative, or Adventure. The default setting is Survival.
4. **DIFFICULTY.** This setting determines the difficulty level of your server. The default option is Normal, but you can change it to Peaceful, Easy, or Hard based on your preference.
5. **ALLOW CHEATS.** To enable in-game cheats, activate this option. By default, it is disabled.

Starting your server:

- Once you have configured all the settings, you can start the server by going to the **"Console"** tab and clicking **"Start"**.
- Wait a few moments for the server to boot. When you see the message:
"[INFO] Done (<number>s)! For help, type "help" or "?"
or
"Server started."
- Your server is fully booted and ready to be joined.


Changing Configurations:

If you wish to change settings not listed in the **Variables** section, you can edit the server's config file located at `/home/container/server.properties`. However, note that any changes to the **Variables** options in the **"Startup"** tab will override the corresponding settings in the config file. We recommend only changing values in the config file that are not listed in the **Startup** tab.

Legal information for your server

When managing your Minecraft server, it's important to adhere to the following legal guidelines:

1. **Minecraft's Usage Guidelines:**
Please review and follow the official Minecraft Usage Guidelines to ensure your server complies with their policies. You can find the guidelines [here](#).
2. **ProRedLine's Terms of Service (ToS):**
Ensure that your server is in compliance with ProRedLine's Terms of Service. You can read the ToS [here](#).
3. **ProRedLine's Acceptable Use Policy (AUP):**
Your server must adhere to ProRedLine's Acceptable Use Policy. Please familiarize yourself with the AUP by reading it [here](#).



By following these guidelines, you can ensure that your server operates within the legal boundaries set by both Minecraft and ProRedLine.

Reinstall your server

If you need to reinstall your server, follow these steps:

1. **Go to the "Settings" Tab:** Navigate to the "Settings" tab in your server dashboard.
2. **Scroll Down:** Look for the option to reinstall your server.
3. **Click on "Reinstall Server":** This button will initiate the reinstallation process.

Important Note: Reinstalling your server will delete all of your current files and configurations. It will replace them with a fresh, clean installation. Make sure to back up any important data before proceeding with this action.

Support for your server

If you have any questions or concerns regarding your server at ProRedLine, you can reach our support team by visiting [ProRedLine Support](#).

For questions specifically related to Minecraft, we recommend contacting Minecraft support directly through their [Help Center](#).